```
# Script: IWATCH-reader-006.R
# Created: January 9, 2021
# Revised: January 10, 2021
# Name : Claus E. Andersen (clan@dtu.dk)
# Use cases of this script:
# 1. Visualize certain radiation physics interactions for teaching such as:
     (a) Impact of magnetic field on individual electrons.
     (b) Electrons passing through air cavity vs. water cavity.
# 2. Illustrate EGSnrc for debugging and teachning purposes such as:
     (a) The stack (NP)
     (b) What happens when Estep is changed?
     (c) Do electrons go straight if we stop straggling?
     (d) What paths will be taken if we enforce CSDA?
# 3. Compute certain interesting features like:
     (a) Projected or maximum range of electrons.
     (b) Electron backscatter fraction.
# Background:
# The RZ-user codes in EGSnrc includes an option to create files with particle/history information.
# Select the I/O-control, and set iwatch = graph. Minimize the number of histories to 1000 or such
# (as the files can become very large).
# The files read by this script have the extension egsgph.
# Note that we have NP (= stack counter) in the egsgph file. We take the
# interpretation that this is the 'generation'. This may not be
# correct.
```

# We compute the loss of energy at each point (dE = E - lead(E)). This value is also

```
# subject to interpretation.
# Looking at the nrcaux.mortran code, we can identify the format of
# the egsgph-file:
\# IF((IWATCH = 4) & (IARG >= 0) & (IARG ~= 5)) [ 'GRAPHICS OUTPUT'
# IF( graph unit < 0 ) graph unit = eqs open file(ku,kr,ka,'.eqsqph');
# WRITE(graph_unit,:GRAPHICS_FORMAT:) NP, IQ(NP), IR(NP), X(NP), Y(NP), Z(NP), E(NP);
# :GRAPHICS_FORMAT:FORMAT(214,1X,16,4G15.8,112);
# There is also a special line with zeros and the value of JHSTRY:
# IF(IWATCH = 4) [
# IF( graph_unit < 0 ) [</pre>
     graph_unit = egs_open_file(ku,kr,ka,'.egsgph');
# WRITE(graph_unit,:GRAPHICS_FORMAT:) 0,0,0,0.0,0.0,0.0,0.0,JHSTRY;
# JHSTRY=JHSTRY+1;
# ]
# NP = stack counter
# IR = region number
# IQ = charge
# Detail: How did I find that file?
# I ran the code:
     grep -rnw 'EGSnrc/HEN_HOUSE' -e 'egsgph'
# to identify all files containing the text string 'egshph'.
```

## Main parameters used in this analysis:

name	value
Time of analysis	2021-01-10-10:04:49
Note	Test case
Input file name	IWATCH100.egsgph
Input file folder	~/EGSnrc/egs_home/dosrznrc/
Output file	<pre>IWATCH-analysis-results-IWATCH100-001</pre>
Electrons, primary (NP=1). color	blue
Electrons, secondary (NP>1). color	black
Photons, primary (NP=1). color	green
Photons, secondary (NP>1). color	green
Positrons, primary (NP=1). color	red
Positrons, secondary (NP>1). color	red













